

## Gas-Vision Software History



Version no.	Instrument	Bug Fixes	Features
5.0	General		Long file names are supported now
	General		XP compatible
	MultiPID 1		No more support of MultiPID 1
	General		Directory to save files can be permanently adjusted
	General		Facelift of interface
	General		Pac Ex 2, X-am 3000 (limited), X-am 7000 now supported
5.6	Pac III	bugfix of Pac III datalogger	
	X-am 3000		improved readout of X-am 3000 (faster)
5.6.5	General	Bugfix regarding the logging of sensors	Improved online measurement
5.6.8	General	Bugfix regarding print out of charts, as no correct date and time was printed	Also the TWA-value between the two cursors will be printed on the print out
	Pac III	All events will be printed in the chart, e.g. also the TWA-value at the end	
5.6.13	X-am 3000	Bugfix regarding date and time setting at online-measurement	Support of Firmware 1.4
	General		Min/Max/Average/TWA output in printout diagramm
5.7.5	Pac 7000		Integration of Pac 7000
	X-am 7000		Integration of X-am 7000 with PID-Sensor
	X-am 2000		Integration of X-am 2000
5.8.0	Pac 7000	Bugfix regarding download of the datalogger Pac 7000	
	General		Identification of DLL releases in Info-Box
5.8.2	Multi PID 2		Integration of Multi PID 2 (Plus)
5.8.4	Pac 7000	Bugfix regarding download of the datalogger Pac 7000	
	X-am 5000		Integration of X-am 5000
5.8.8	General	Single sessions selectable with datalogger larger than 100 sessions.	
	Pac 7000		Support of Pac 7000 V2.2
5.8.9	X-am 5000	New X-am 5000 DLL integrated (V3.0.016): bugfix if datalogger is full and in roll mode	

	General		COM-Ports >8 available
	X-am 5000		New X-am 5000 DLL integrated (V3.0.016)
5.9.2	X-am 5600		New X-am 5000 DLL (V3.0.019) with X-am 5600 integrated
	General		Support of Windows 7 (32 bit)
5.9.4	General		Support of Windows 7 (64 bit)
5.9.7	General		Support of Cat-Ex 125 PR
5.9.8	General		Improvement of multi-session selection
6.0.2 Release 16.01.2013	X-dock		Support of X-dock data loggers
	X-am 125		Support of X-am 2500
6.0.4 11.02.2013	X-dock	Fix for Pac data loggers read by X-dock	
7.0.0 15.11.2014	General		Design Facelift (icons, colors, layout...)
			Excel-Export
			Automatic USB detection
			Introduction of key based license concept
			Improved session handling (sidebar)
			Improved chart navigation
			Improved print process
		Long Session Handling	
7.0.1 12.05.2015	Pac Series	Fix in data logger DLL for Pac instruments. Date and time are now correct.	
7.2 29.11.2017	X-am 8000		Support of X-am 8000
7.2.2 05.03.2018	Pac 6X/8X00		Support of Pac 6X/8X00
7.2.3 22.06.2018	XDM	Bug fixed during data transfer of data logs	Support of X-am 3500
7.2.8 10.07.2019	General		performance improved for online-measurements
	General		column width fixes
	General		TWA calculation with own graph added
	General		STEL calculation with own graph added
	X-am 8000		Data handling improvements and language files updated
	All devices		DLLs updated
7.3.2	X-pid 9000/9500		Integration of X-pid 9000/9500 measuring datas in Gas Vision

19.05.2020	Polytron 7000		Removing of uploading datalogger from Polytron 7000
	General		Improvement of excel-export
7.3.7 23.06.2020	X-pid 9000/9500		Bug Fix: open files for X-pid
	General		Bug Fix: excel-export
7.3.9 01.11.2021	General		added new datalogger
	General		new functionalities on graphic
7.3.9-16 19.04.2022	General		Bug Fix: licensing trail-version
8.0.0 31.08.2022	X-am 2800		Support of X-am 2800
8.0.1 12.04.2023	General		general bug fixes
	General		new device librarys for Pac and X-am devices
8.0.2 30.08.2023	General		general bug fixes
	General		new device librarys for Pac and X-am devices
	General		Bug Fix open files and excel-export
8.0.5 03.04.2024	General		general bug fixes
	General		new device librarys for Pac and X-am devices

